Mapping a Drive on RDS (Windows)


How to map a drive to the RDS server (rds6.cchmc.org) in Windows 7 & Windows 10.

Download a PDF copy of this document: RESITHUB-MappingRDSWin-240423-1600-868.pdf.

(i) Getting Access to a Drive

- If access has not yet been requested for you, you can submit a request yourself in Permissions Manager. The submitted request will need to be approved by any one of the authorizers, who are automatically notified when you submit the request. When the authorizer has handled your request, you will be automatically notified via an email from Permissions Manager.
- After being granted access to a drive, you must restart your computer before mapping a drive to it. If you are denied access to a drive, please restart your computer and try mapping it again.
- Authorizers can grant access to users via the Permissions Manager. Authorizers do not automatically have access, but they can grant access to themselves.
- The Permissions Manager can be accessed here: htt ps://bmirdsdp.chmccorp.cchmc.org/dp/.
- Instructions on how to use Permissions Manager are here: https://confluence.research.cchmc.org/x /dgNcAw.
- You must be connected to a CCHMC network to access a project drive.
 - If you are on-site this means your computer is plugged-in with an ethernet cable or you are connected to the "chmc-bus" wireless. The "childrens-guest" wireless will not allow you to access project drives.
 - If you are remote you must be connected to either the CORP VPN (connect.cchmc.org) or RES VPN (asa.research.cchmc.org). Both RDS6 and BMIISI project drives are accessible through either VPN.

1. Right-click **This PC** on your desktop and select **Map Network Drive**. You can also right-click This PC in File Explorer or select Map Network Drive from the File Explorer "Computer" menu:




📃 🌛 🔜 🗢 This PC					
File Computer V	ïew				
Properties Open Rename	Access media •		k Add a network location	Open Settings	💽 Uninstall 🕎 System pr 🔂 Manage
Location		🛖 Mapin	etwork drive		Syst
🕂 Downloads		💼 Discor	nnect network driv	e	000,000
Documents			*		Downloads
Pictures			Я		

2. The "Map Network Drive" window should appear. For the **Drive** field, select the letter you want to assign to the network folder you're mapping. In the **Folder** field, type or paste the address of the folder you would like to map. For example, if you are mapping your division's shared folder on the Research Data Storage (RDS) system, you would probably select "G:" for the Drive and enter "\\rds6.cchmc. org\YourDivision-s" for the folder path. In the screenshot below we are using "\\rds6.cchmc.corp.cchmc.org\Cardio-S" for the folder path.

	×	
÷	🚴 Map Network Drive	
	What network folder would you like to map? Specify the drive letter for the connection and the folder that you want to connect to:	
	Drive: G: Folder: \\rds6.chmccorp.cchmc.org\Cardio-S v Browse Example: \\server\share Reconnect at sign-in Connect using different credentials Connect to a Web site that you can use to store your documents and pictures.	
	Finish Cancel	

- 3. Check the box to "Reconnect at sign-in" and click the Finish button.
- 4. If prompted for your network credentials in the "Windows Security" window, enter your CCHMC User ID and password.

4	Connecting from a Personal Computer
	If you are mapping a drive on your personal computer, you will:
	 need to be connected the VPN, and enter your User ID as "chmccorp\userid".



Getting additional help

If there are still any issues after reading these instructions and any help is still needed, please email help-rds@bmi.cchmc.org or call the Service Desk at 636.4100 for further assistance.